
EPSON RC+ 7.3.4 Release Notes

February 23, 2018

Thank you for using EPSON RC+ 7.3.4. This document contains the latest information for this release. Please read before using this software.

DOCUMENTATION.....	2
GETTING STARTED	2
WHAT'S NEW IN VERSION 7.3.4	2
WHAT'S FIXED IN VERSION 7.3.4	2

Documentation

All RC+ manuals are in PDF format and are installed on the PC hard disk. These manuals are accessible from the EPSON RC+ 7.0 environment Help menu.

Getting Started

Read the Getting Started chapter in the EPSON RC+ 7.0 User's Guide. This chapter will refer you to the RC700 Controller manual Installation chapter. This contains information for initial connections and start up.

What's New in version 7.3.4

1. Supports the T6 and N6 robots.
2. Simulator objects can now be changed at runtime.

What's Fixed in version 7.3.4

1. Fixed a problem for GUI Builder VideoBox in auto mode. If the ImageSize property of the sequence being displayed is not default, then the vision graphics scale was wrong.
2. Fixed a problem for remote I/O save and load. Remote signals that use multiple bits (e.g. PositionX) were not restored after loading the settings from a file.
3. Fixed a problem that the change of the language preferences was not applied immediately in the simulator.