

EPSON RC+ 7.4.4 Release Notes

December 27, 2018

Thank you for using EPSON RC+ 7.4.4. This document contains the latest information for this release. Please read before using this software.

DOCUMENTATION	2
GETTING STARTED	2
WHAT'S NEW IN VERSION 7.4.4	2
WHAT'S FIXED IN VERSION 7.4.4	2
VISION GUIDE	2
CAMERA & LENS SELECTION TOOL	2
PARAMETER TUNING TOOL.....	2

Documentation

All RC+ manuals are in PDF format and are installed on the PC hard disk. These manuals are accessible from the EPSON RC+ 7.0 environment Help menu.

Getting Started

Read the Getting Started chapter in the EPSON RC+ 7.0 User's Guide. This chapter will refer you to the RC700 Controller manual Installation chapter. This contains information for initial connections and start up.

What's New in version 7.4.4

1. Supports LS3-B robot.

What's Fixed in version 7.4.4

Vision Guide

1. Added support for acA3800-10gc GigE camera for PC Vision and CV2-A Compact Vision. CV firmware 3.1.0.5 or greater must be used when using CV2-A Compact Vision..
2. Fixed a problem for ImageOp when SearchWinType is RotatedRectangle and a frame is used. The ImageOp search window was not being rotated in the frame.
3. Fixed VDeleteSequence when Compact Vision is used and there is no PC Vision license. An undefined sequence error was occurring.

Vision Guide

Camera & Lens Selection Tool

A camera and lens selection tool is provided in the EpsonRC70\Tools folder after installation. A PDF file with instructions is provided in the folder.

Parameter Tuning Tool

A sample project for a vision parameter tuning tool is provided in EpsonRC70\Projects\Samples\Vision\VGTuningTool. A PDF file with instructions is provided in the folder. The GUI Builder option is required to use this tool.